



https://mam-automation.live - Manual Guide

1. Installation:

- Download the product's package, you will see the "https://mam-automation.live- Royal Robot Rewards.ex4" and "https://mam-automation.live - Royal Robot Rewards.ex5".
- Open your receiver MT4/MT5 platform -> Main menu -> Tools -> Options -> Expert Advisors -> Enable "Allow automated trading", "Allow DLL imports", "Allow WebRequest for listed URL", and add URL " <http://my.mam-automation.live>" as following:




- Go to MT4 or MT5 data folder by main menu -> Files -> Open Data Folder. It will open data folder of your terminal.
- Copy "https://mam-automation.live Royal Robot Rewards.ex4" (if you use MT4) or "https://mam-automation.live - Royal Robot Rewards.ex5" (if you use MT5) file to directory path: /[data folder]/MQL4(5)/Experts/.
- Go back to MT4/MT5 terminal -> Main Menu -> View -> Navigator -> Right click on Expert Advisors folder -> Refresh -> Find "Royal Robot Rewards.ex4" -> Double click or drag it into any chart.
- At startup window -> Common tab -> Enable "Allow DLL imports" and "Allow live trading" check box.



2. Connect to the provider


- First, you have to ensure that your account number has been added to the <http://mam-automation.live> has enabled his copier already.
- After confirm that, you need to add the provider's account number to allowed list on your side. Please note that you can only add the <http://mam-automation.live> has been added you already on his side.



The screenshot shows the 'SETTINGS' window of the 'Trade Receiver Free' application. The window has a title bar with the text 'Trade Receiver Free' and standard window controls. The main content area is titled 'SETTINGS' and contains the following elements:

- A status indicator: 'This is receiver's account' with a speaker icon.
- A button: 'Provider List >>>'.
- Mode selection: 'Mode : ☒ Remote ☐ Local'.
- Transmission data selection: 'Transmission data : ☒ Trade ☐ Alert'.
- Max. slippage: 'Max. slippage : 50 point(s)'.
- Set lotsize by: 'Set lotsize by : Provider risk scaling' (dropdown menu).
- Scale factor: 'Scale factor : 1.00'.
- Max. Lotsize: 'Max. Lotsize : 0.00 (unlimited)'.
- If Equity DD reach: 'If Equity DD reach : 50.00 %, Close All Trades' (dropdown menu).
- Copy Filter: 'Copy Filter : ☒ Entry ☒ SL ☒ TP ☒ Exit'.
- Order Filter: 'Order Filter : ☒ Buy ☒ Sell ☒ Pending'.
- Custom pair: '☐ Custom pair'.
- Inverted copy: '☐ Inverted copy (Buy<-->Sell)'.

Below the settings is an 'ACTIVE STATUS' section with the text 'Active Status: ENABLED' and 'Connected to all providers'.



The screenshot shows the 'PROVIDER LIST MANAGER' window of the 'Trade Receiver Free' application. The window has a title bar with the text 'Trade Receiver Free' and standard window controls. The main content area is titled 'PROVIDER LIST MANAGER' and contains the following elements:

- A search bar: 'Keyword...' with a magnifying glass icon and a 'SEARCH' button.
- A list of providers: A list box containing one entry: '91649940 - Provider 1'.
- Add provider section: 'Add provider:' with two input fields: 'Account number' and 'Description', followed by a '+' button.
- An 'OK' button at the bottom.


- After adding the provider, now enable the copier at receiver's side by clicking to Status button at the bottom of the panel. If they are connected, the screen icon at both sides will blinking.

- **Remote/Local mode:** Choose between Remote and Local mode. Remote mode allows to copy between accounts at different locations over internet. Local mode only allows to copy between accounts on the same PC/Server. In the Local mode, trades are copied nearly instant (<0.1 second). In the Remote mode, due to internet connection speed, it may be a bit slower.
- **Transmission data:** Choose how data will be sent/received. It can be either "Trade" (receiver's account trades follow the provider's) or "Signal" (receiver's account only receives signal alert). Provider's choice is priority: If provider choose "Trade", then receiver can receive trade or signal due to his choice; If provider choose "Signal", then receiver can only receive signal despite of his choice.
- **Max. slippage (for receiver only):** Maximum accepted slippage to copy trades. Price might be different between brokers, so if the current price of the receiver's account exceed max. slippage distance compared to entry price of provider's account, the trade will not be copied. This is useful to prevent unwanted slippage of copied trades, specially during high volatility (news releases). You can even set Max. slippage as 0 or negative to copy equal or better price than provider's entry.
- **Set lotsize by:** Choose how the trade volume on receiver's account will be set. There are 5 options:
 - **Provider risk scaling:** Receiver's lotsize will be set so that it scale by a scale factor with the provider's risk. This is recommended option because it make receiver's account has the same growth/risk rate as provider's. Example: Provider trades 0.5 lot with balance 1000\$ --> Receiver with balance 2000\$ and scale factor 1 will trade 1.0 lot. Receiver with balance 2000\$ and scale factor 2 will trade 2.0 lot.
 - **Multiplied by provider's lotsize:** Lotsize will be multiply by a factor with Provider's lotsize. Only use this option if you know the lotsize setting manner of the provider, otherwise you may suffer whipsaw by over lotsize. Example: If multiply factor is set as 2 and provider open 1 lot, then receiver will open 2 lot. If multiply factor is set as 1, then receiver will always open the same lot as provider.
 - **Ratio with receiver's balance:** Lotsize will be scaled with receiver's balance. Example: Lotsize is 1 lot if balance is 1000\$, then lotsize will be 1.5 lot when balance is 1500\$.
 - **Fixed lotsize:** Every trades on receiver's account will be set with a fixed lotsize regardless of provider's lotsize or receiver's balance.
 - **Custom risk percentage:** Enter a specify risk percentage for each trade if stoploss occur. Example: A trade with 20pip stoploss is copied, receiver's lotsize will be set so that if stoploss occur receiver will lose 5% of balance. This regime is only applied for trades with predefined stoploss; with no-stoploss trades, "Provider's lotsize scale" regime will be applied.
- **Max. lotsize:** Maximum allowed lotsize for each trade. This will prevent your account from open unanticipated over lotsize that may lead to unwanted drawdown.
- **Max Equity DD %:** Maximum equity drawdown percentage allowed. If account equity drawdown reach this level, the copier will take one of the following actions:
 - **Close All Trades:** Close all opening trades and delete all pending orders.
 - **Stop Copy:** Stop copying new trades, but still keep following the opening trades.
 - **Close & Stop Copy:** Close all opening trades and delete all pending orders. Also, stop copying new trades, but still keep following the opening trades.
 - **Close Win Trades:** Close all winning trades.

- **Close Lose Trades:** Close all losing trades.
- **Copy filter:** Select which exit parameter receiver will copy from provider. With this option, receiver can has its own exit strategy by manual or other EAs without relying on provider.
- **Copy filter (for receiver only):** Select which trade's parameter receiver will be copied from provider:
 - **Entry:** Copy every trades from provider. If you disable this, it will only manage the copied trades, without copying new ones.
 - **SL:** Copy every Stoploss changes from provider.
 - **TP:** Copy every TakeProfit changes from provider
 - **Exit:** Copy exit points from provider. If you disable this, you must exit the copied trades on your own.
- **Order filter:** Select which types of orders will be copied. Some filters are for both provider and receiver, but provider's choice is priority. There are multi-options:
 - **Buy orders:** Buy orders will be copied.
 - **Sell orders:** Sell orders will be copied.
 - **Pending orders:** Pending orders will be copied.
 - **Custom pair:** Only copy trade of custom pair (combine with order types above). You can input multiple pairs by putting comma (,) or semicolon (;) between them. E.g: EURUSD; GBPUSD; USDJPY. You can also exclude the pairs by putting exclamation (!) in front of the pairs. E.g: !EURUSD; !GBPUSD; !USDJPY.
- **Inverted copy:** All filtered trades will be inverted when come to/from receiver/provider: Buy<-->Sell, BuyLimit<-->SellStop, BuyStop<-->SellLimit, Stoploss<-->Takeprofit.

4. Other configurations

You can change some more configurations by clicking on menu icon on the header



- **Using account list:** Show up the list of account numbers that using this product with your license. If the maximum amount is exceeded, you should either remove it from one of using accounts or purchase more license to increase this maximum quota.
- **Special symbols setting:** Config up to 5 special pair symbols synchronization. Currency symbols will be auto recognized, but some special symbol pairs are different between brokers and may need to be setup manually, such as: GOLD -> XAUUSD, SILVER -> XAGUSD, etc.,
- **Fontsize setting:** Change the font size of interface if it's too small or too large for your screen resolution.

- **Reset to default settings:** Reset all the settings back to manufactured settings.
- **Check for update:** Check the latest version and update if it is available.

RRR Software Program - Manual Guide | <https://mam-automation.live>